


Setting Up a Connection Manually

To access a database with DbVisualizer, you must first create and setup a Database Connection. The easiest way to set up a connection is to use the [Connection Wizard](#), but you can also do it manually.

Setting Up a Connection Manually

1. Create a new connection from **Database->Create Database Connection** and click **No Wizard** when prompted. An **Object View** tab for the new connection is opened,



2. Enter a name for the connection in the **Name** field, and optionally enter a description of the connection in the **Notes** field,
3. Leave the **Database Type** as **Auto Detect**,
4. Select an installed **JDBC driver** (marked with a green checkmark) from the Driver (JDBC) list (see [Installing a JDBC Driver](#) for how to install a JDBC driver manually),
5. Enter information about the database server in the remaining fields (see below for details),
6. Verify that a network connection can be established to the specified address and port by clicking the **Ping Server** button,
7. If Ping Server shows that the server can be reached, click **Connect** to actually connect to the database server.

See [Fixing Connection Issues](#) for some tips if you have problems connecting to the database.

Alternatively, you can set the **Settings Format** to **Database URL** (this is the only choice for some custom JDBC drivers). This replaces the fields for information about the database server with a single **Database URL** field, where you can enter the JDBC URL.

The information about the database server that needs to be entered depends on the which JDBC driver you use. For most drivers, you need to specify:

Field	Description
Database Server	The IP address or DNS name for the server where the database runs.
Database Port	The TCP/IP port used by the database.
Database Userid	The database user account name. Enter (null) to not send an account name.

Database Password	The database user account password. Enter (null) to not send a password.
--------------------------	--

For some database such as Oracle, you may use a [TNS name](#) instead of specifying the server and port. Other drivers may add more fields that are driver specific.

You may also optionally specify [SSH tunneling information](#) and Options, such as:

Option	Description
Auto Commit	Check if you want to enable auto commit in the SQL Commander by default for the connection.
Save Database Password	Check if you want the password to be saved (encrypted) during the session, between sessions, or cleared when you disconnect.
Permission Mode	One of Development , Test or Production to select which set of Permissions to use.

See the [Configuring Connection Properties](#) page for related topics.